### TECHNICAL ENGINEERING & ASSISTANCE TEAM

HELPDESK INFORMATION

TE&AT EAST (910) 554-9992 TE&AT WEST (760) 439-4278 TDIS\_EAST\_SUPPORT@NGC.COM TDIS WEST SUPPORT@NGC.COM



**QUICK NOTES 6-09** 

# MDSS II 7.2 (CMOS Export)

Date: 12 February 2009

Quick Notes Objective: To provide the operational forces a concise guide on how to perform MDSS II


7.2 CMOS export of data from a Unit Deployment List (UDL).

## **MDSS II 7.2 CMOS EXPORT PROCESS**

The MDSS II 7.2 Cargo Movement Operations System (CMOS) export allows for the export of unit move data from the MDSS II UDL to assist the local Traffic Management Office in the commercial booking of transportation. The export process provides the option to select records from the UDL, select a particular Mission and all the records associated with it.

NOTE: Prior to executing a CMOS export a certain level of detail needs to be resident in the MDSS UDL. When exporting individual records from the UDL, TCNs need to be generated. Prior to exporting by Mission, ULNs should have been entered in the "ULN HDR" table and assigned to the appropriate records, TCMD information should have been generated by executing either an MDSS II WPS or GTN export, and finally, the actual mission created in the Embarkation Workbench with appropriate cargo/equipment assigned to the mission. Unless the "mission" is created in the MDSS II Embarkation Workbench it will not appear in the "CMOS Export Selection" window "Mission" tab.

- 1. Ensure the correct MDSS II plan that the data will be exported from is the active plan.
- 2. Select **<Interfaces**>, **<Export**> and the "**Export**" window will display.



### TECHNICAL ENGINEERING & ASSISTANCE TEAM

HELPDESK INFORMATION

TE&AT EAST (910) 554-9992 TE&AT WEST (760) 439-4278

TDIS\_EAST\_SUPPORT@NGC.COM TDIS WEST SUPPORT@NGC.COM




**QUICK NOTES 6-09** 

- 3. In the "Interface Type:" box select < CMOS (\*.txt)>, then select the appropriate Drive and Directory to generate the file to.
- 4. In the "File Name" box, type the appropriate name for the export file then click **<OK>** and the "CMOS Export Selection" window displays.



- 5. In the "Enter the Consignor's DODAAC" box, click the drop down arrow and select the appropriate DODAAC. Note: In most cases the "Consignor" will be the installation TMO that facilitating the shipment.
- 6. In the "and the Consignee's DODAAC" box, click the drop down arrow and select the appropriate DODAAC. Note: In most cases the "Consignee" will be the TMO at the installation that the shipment is going to.
- 7. To Export a mission with the "**Mission**" tab active, highlight the appropriate Strategic mission and select **<OK>**.

NOTE: You can select only one mission at a time.



Note: Additional information required by the TMO facilitating the shipment is what unit the shipment will be "Marked For" (MF) at the destination. In the "Mission" tab, only the Strategic leg (POE-POD) will include the Transportation Account Code (TAC) in the export.

### TECHNICAL ENGINEERING & ASSISTANCE TEAM

HELPDESK INFORMATION


TE&AT EAST (910) 554-9992 TE&AT WEST (760) 439-4278 TDIS\_EAST\_SUPPORT@NGC.COM TDIS WEST SUPPORT@NGC.COM



**QUICK NOTES 6-09** 

8. To Export a UDL Record(s) with the UDL tab active, highlight the appropriate UDL record(s).

NOTE: You can select more than one record by holding the Ctrl or Shift key down while clicking on the record(s).



Note: Additional information required by the TMO facilitating the shipment is to what unit the shipment will be "Marked For" (MF) at the destination. When selecting by the "UDL" tab the Transportation Account Code (TAC) is not included in the export and must also be provided to the TMO.

9. After either of the aforementioned selection processes, click the **<OK>** button. Then select **<OK>** on the "**CMOS export is completed**" dialog box.